

COMBO™ ORDER FORM

Instructions for ordering an assembled Allard COMBO™

COMBO™ can only be assembled to the following AFOs:

ToeOFF® Original / ToeOFF® 2.0 / ToeOFF® 2 ½ / BlueROCKER® Original / BlueROCKER® 2.0, BlueROCKER® 2 ½.

COMBO™ cannot be assemble to:


ToeOFF® Flow 2 ½ / ToeOFF® Short / BlueROCKER® Short

Please note: Maximum body weight for COMBO™ is 150Kg and height of 2 metres.

Company / Hospital:	
Orthotist:	
Contact Telephone Number and / or Email:	
Customer Reference:	
Patient ID:	
Patient Height:	
Patient Weight:	
Has the patient previously had a COMBO™?	
If so, please provide order number:	
Which AFO from the allowed list above does the patient require?	
Does the patient require Left, Right or Bilateral? If Bilateral, be sure to complete this Form and Template for both Left and Right side.	
What size is required?	
Does the patient require a SoftKIT or ComfortKIT?	

Please follow the process below to provide sufficient information for Allard UK to assemble the COMBO for your patient:


- 1 Evaluate the patient's functional leg position and relative Toe in/out while standing. That position will always be replicated when fabricating a COMBO™.
- 2 Have the Patient in supine position with the AFO donned. Make sure the legs are parallel and in natural toe in/out position.



Record Toe position below:

- Patient is In Toe Position
- Patient is out Toe Position?


- 3 Place the Template enclosed from this pack under the Patient's leg. Line up the Patient's Tibial Plateau with the line marked 'Tibial Plateau' on the Template.
- 4 The Thigh Cuff should have a snug fit. To ensure the correct size is selected, measure the Circumference and M-L at Knee Centre



Measurements:

- Circumference at Knee Centre _____cm
- M - L measurement at Knee Centre _____cm
- Circumference 20cm above Mid Patella _____cm
- M-L measurement 20cm above Mid Patella _____cm

- 5 Choose the correct size Thigh Cuff using the measurements taken in (4.) above. Position the Thigh Cuff, which should be at least 10cm above the Tibial Plateau.
- 6 Trace the bottom of the Thigh Cuff onto the Template.
- 7 Mark the Wings of the AFO (left and right side) onto the Template.
- 8 Measure the height from heel of AFO to inside Thigh as well as to Tibia Plateau.



Measurements:

- Height from heel of AFO to inside Thigh _____cm
- Height from heel of AFO to Tibia plateau _____cm

By submitting this form you are certifying that personal data has been processed in compliance with GDPR (EU) 2016/679. The data will be processed only to the extent necessary to deliver ordered products. Due to the Data Privacy Regulation GDPR (EU) 2016/679 this form must be submitted through <https://submit.allardsupport.com>.

Please send the completed COMBO™ Order Form and the prepared Template to:
Allard Support UK Ltd , Coes Road, Dundalk, A91 E868, Co. Louth, Ireland
 Should you have any queries, please contact us at: customerservice@allarduk.co.uk

COMBO™ ORDERING TEMPLATE

Bottom of Thigh Cuff must be positioned
at least 10cm above Tibial Plateau

TIBIAL PLATEAU